

JumpServer documentation (en)

- [Installation](#)
 - [Installation JumpServer Enterprise Edition](#)
 - [Installation JumpServer Community Edition](#)
 - [Operation and Maintenance with command line jmsctl](#)
 - [JumpServer port discription](#)
 - [Installing SSL Certificates and Configuring HTTPS](#)
 - [HAProxy configuration for JumpServer HA-cluster](#)
 - [JumpServer HA-cluster configuration](#)
- [Getting Started Guide](#)
 - [Getting Started Guide for JumpServer PoC](#)
- [Main configuration](#)
 - [Active Directory synchronization with AD groups](#)
 - [Command filter configuration for SSH and database queries](#)
 - [How to enable 2FA\(TOTP\) auth](#)
 - [Installing OpenSSH for account management for Windows](#)
 - [Syslog configuration](#)
 - [RemoteApp configuration for application publishing](#)
 - [How to configure access to asset web-interface, HTTP session configuration](#)
 - [Setting up Panda for application publishing\(alternative to RemoteApp\)](#)
- [Troubleshooting](#)
 - [How to check system status and container logs](#)
 - [RemoteApp Troubleshooting](#)

- Additional features
 - Custom Applet structure for RemoteApp

Installation

Installation JumpServer Enterprise Edition

To begin, you need to request the latest distribution file from us via email at info@afid.com or on Telegram: [@mapceaheh](https://t.me/mapceaheh).

1. System Requirements:

- OS: Linux/AMD64 (arm64) x86_64(aarch64) kernel version 4.0 or higher (preferably Redhat, Debian, Ubuntu families)
- CPU: 4 cores
- RAM: 8 GB
- HDD: 60 GB

2. Installation

Place the downloaded file in the directory **/opt**

Execute the following commands (file names may vary with new versions):

```
$ cd /opt
$ tar -xf jumpserver-offline-installer-v3.10.3-amd64.tar.gz
$ cd jumpserver-offline-installer-v3.10.3-amd64
```

Next, you can edit the configuration file to change installation parameters, for example, to use an external MySQL database or change the installation folder.

```
# nano /opt/jumpserver-offline-installer-v3.10.3-amd64/config-example.txt
```

Start the installation:

```
# cd jumpserver-offline-installer-v3.10.3-amd64
# ./jmsctl.sh install
```

During installation, you will need to confirm the data entered in the configuration file or provide other data if you did not fill in the configuration file in advance.

Start the application:

```
# ./jmsctl.sh start
```

3. Start application

Navigate to the product folder (the folder name may change with new versions) and start application:

```
# cd /opt/jumpserver-installer-v3.10.3  
# ./jmsctl.sh start
```

After this, you can access the web interface at:

http://IP/ Login: **admin**

Password: **ChangeMe**

and begin configuring the system.

Installation JumpServer Community Edition

Attention: You will not be able to install a license to activate Enterprise (x-pack) features in the Community Edition. If you plan to do PoC of Enterprise version, follow the installation instructions for JumpServer Enterprise Edition.

1. Server preparation

System Requirements:

- OS: Linux/AMD64 (arm64) x86_64(aarch64) kernel version 4.0 or higher
- CPU: 4 cores
- RAM: 8 GB
- HDD: 60 GB

Installation of additional components on Debian\Ubuntu as an example:

```
# apt-get update
# apt-get install -y wget curl tar gettext iptables
```

2. JumpServer Installation

Quick Online JumpServer Installation:

In this case, JumpServer will be installed with default parameters, and MySQL and Redis databases will be installed in containers on the same server.

```
$ curl -sSL https://github.com/jumpserver/jumpserver/releases/latest/download/quick_start.sh | bash
```

Wait for the script execution to complete.

Standard Online Installation:

Download the latest installer from GitHub: <https://github.com/jumpserver/installer/releases> Below are example commands for version 3.10.3:

```
# cd /opt/
# wget https://github.com/jumpserver/installer/releases/download/v3.10.3/jumpserver-installer-v3.10.3.t
# tar -xf jumpserver-installer-v3.10.3.tar.gz
```

Next, you can edit the configuration file to change installation parameters, for example, to use an external MySQL database or change the installation folder for cluster installation etc.

```
# nano /opt/jumpserver-installer-v3.10.3/config-example.txt
```

Start the installation:

```
# cd ./jumpserver-installer-v3.10.3  
# ./jmsctl.sh install
```

During installation, you will need to confirm the data entered in the configuration file or provide other data if you did not fill in the configuration file in advance.

3. Starting the Application

After the installation is complete, navigate to the product folder (the folder name may change with new versions) and start the application:

```
$ cd /opt/jumpserver-installer-v3.10.3  
# ./jmsctl.sh start
```

After that, you can access the web interface at:

<http://IP/> Login: **admin**
Password: **ChangeMe**

and begin configuring the system.

Operation and Maintenance with command line jmsctl

Operation and Maintenance - jmsctl

JumpServer includes a built-in command-line tool for operation and maintenance by default - **jmsctl**. To view the help documentation, run the command:

```
jmsctl help
```

JumpServer Application Management:

```
./jmsctl.sh [COMMAND] [ARGS...]  
./jmsctl.sh --help
```

Installation Commands:

- install - Install the JumpServer service

Management Commands:

- config - Configure the tool, run jmsctl config --help to view help
- start - Start the JumpServer service
- stop - Stop the JumpServer service
- restart - Restart the JumpServer service
- status - Check the status of the JumpServer service
- down - Stop the JumpServer service
- uninstall - Uninstall the JumpServer service

Additional Commands:

- load_image - Load a Docker image
- backup_db - Backup the JumpServer database
- restore_db [file] - Restore data from a database backup file
- raw - Execute a docker compose command
- tail [service] - View service logs

JumpServer port discription

List of Network Ports

JumpServer requires the following network ports to be open for proper operation. Administrators can open the appropriate ports in the network and on the host depending on the deployment scheme of JumpServer components.

Port	Purpose	Description
22	SSH	Installation, updates, and management
80	Web HTTP Service	Access to the JumpServer web interface via HTTP
443	Web HTTPS Service	Access to the JumpServer web interface via HTTPS
3306	Database Service	Used by MySQL
6379	Database Service	Used by Redis
3389	Razor Service Port	Connection to Windows assets via RDP Client
2222	SSH Client	Connection to JumpServer via terminal tools (Xshell, PuTTY, etc.)
33061	Magnus MySQL Service Port	Connection to MySQL via DB Client
33062	Magnus MariaDB Service Port	Connection to MariaDB via DB Client
54320	Magnus PostgreSQL Port	Connection to PostgreSQL via DB Client
63790	Magnus Redis Port	Connection to Redis via DB Client
30000-30100	Magnus Oracle Ports	Connection to Oracle via DB Client, port range can be configured

Installing SSL Certificates and Configuring HTTPS

What is the Purpose of JumpServer Reverse Proxy?

Nginx supports secure WebSockets (wss://), managing connections and securing the channel with an SSL certificate. To enable the copy-paste functionality in the RDP protocol, a trusted SSL certificate must be deployed. Copy-paste in RDP assets is only possible when accessed via the HTTPS protocol.

Installing SSL Certificates and Configuring HTTPS for the Web Interface

Prepare an SSL certificate (note that the certificate **must be in PEM format**). Certificates should be placed in the directory **/opt/jumpserver/config/nginx/cert**

Stop the JumpServer service:

```
./jmsctl.sh stop
```

Open the JumpServer configuration file:

```
vi /opt/jumpserver/config/config.txt
```

Find and update the Nginx configuration parameters:

```
## Nginx Configuration
HTTP_PORT=80
SSH_PORT=2222
RDP_PORT=3389

## HTTPS Configuration
HTTPS_PORT=443          # External port for HTTPS, default is 443
SERVER_NAME=www.domain.com # Your domain for HTTPS
SSL_CERTIFICATE=xxx.pem   # Your certificate name in /opt/jumpserver/config/nginx/cert
SSL_CERTIFICATE_KEY=xxx.key # Your key file name in /opt/jumpserver/config/nginx/cert
```

Save the configuration changes and start JumpServer:

```
./jmsctl.sh start
```

If you need to further edit the Nginx configuration file:

```
vi /opt/jumpserver/config/nginx/lb_http_server.conf
```

Multi-Level Reverse Proxy on Nginx

Hint:

This configuration is suitable when there is a shared external proxy server at the top level. It is an example of multi-level reverse proxying on Nginx. Each proxy section must be configured to support long WebSocket connections.

Editing the Configuration File:

```
vi /etc/nginx/conf.d/jumpserver.conf
```

Example Configuration without SSL:

```
server {  
  
    listen 80;  
    server_name demo.jumpserver.org; # Replace with your domain  
  
    client_max_body_size 4096m; # Limit for maximum file upload size  
  
    location / {  
        # Specify the IP address of the JumpServer Nginx server  
        proxy_pass http://192.168.244.144;  
        proxy_http_version 1.1;  
        proxy_buffering off;  
        proxy_request_buffering off;  
        proxy_set_header Upgrade $http_upgrade;  
        proxy_set_header Connection "upgrade";  
        proxy_set_header Host $host;  
        proxy_set_header X-Forwarded-For $remote_addr;  
    }  
}
```

Recommendation:

For more secure access, it is recommended to configure SSL and use the HTTPS protocol, following the guidelines from [Mozilla SSL Configuration Generator](#).

Example Configuration with SSL:

Redirecting HTTP to HTTPS:

```
server {  
    listen 80;  
    server_name demo.jumpserver.org; # Replace with your domain  
    return 301 https://$server_name$request_uri; # Redirect all HTTP requests to HTTPS  
}
```

Configuring HTTPS:

```
server {
    listen 443 ssl http2;
    server_name demo.jumpserver.org; # Replace with your domain
    ssl_certificate sslkey/1_jumpserver.org_bundle.crt; # Path to your SSL certificate
    ssl_certificate_key sslkey/2_jumpserver.org_bundle.key; # Path to your certificate key
    ssl_session_timeout 1d;
    ssl_session_cache shared:MozSSL:10m;
    ssl_ciphers ECDHE-ECDSA-AES128-GCM-SHA256:ECDHE-RSA-AES128-GCM-SHA256:ECDHE-ECDSA-
AES256-GCM-SHA384:ECDHE-RSA-AES256-GCM-SHA384:ECDHE-ECDSA-CHACHA20-POLY1305:ECDHE-
RSA-CHACHA20-POLY1305:DHE-RSA-AES128-GCM-SHA256:DHE-RSA-AES256-GCM-SHA384;
    ssl_prefer_server_ciphers off;
    ssl_protocols TLSv1.1 TLSv1.2;
    add_header Strict-Transport-Security "max-age=63072000" always;

    client_max_body_size 4096m; # Limit for maximum file upload size

    location / {
        # Specify the IP address of the JumpServer Nginx server
        proxy_pass http://192.168.244.144;
        proxy_http_version 1.1;
        proxy_buffering off;
        proxy_request_buffering off;
        proxy_set_header Upgrade $http_upgrade;
        proxy_set_header Connection "upgrade";
        proxy_set_header Host $host;
        proxy_set_header X-Forwarded-For $remote_addr;
    }
}
```

3. Other Load Balancers (SLB)

Hint:

1. Correctly configure long WebSocket connection support.
2. Consider session management issues.

Installation

HAProxy configuration for JumpServer HA-cluster

HAProxy (High Availability Proxy) — is an **open-source software tool** used for load balancing and traffic proxying at the network protocol level, typically employed to distribute traffic across multiple servers. It is one of the most popular solutions for enhancing the availability and performance of web applications and services.

To install HAProxy on Ubuntu:

```
sudo apt install haproxy -y
```

After installation, you need to edit the configuration file, which is the main aspect of setting up HAProxy. The configuration file is typically located at **/etc/haproxy/haproxy.cfg**.

Example Configuration File from the Vendor's Documentation:

```
global
  log      127.0.0.1 local2
  chroot   /var/lib/haproxy
  pidfile  /var/run/haproxy.pid
  maxconn  4000
  user     haproxy
  group    haproxy
  daemon
  stats socket /var/lib/haproxy/stats

defaults
  log            global
  option         dontlognull
  option         redispatch
  retries        3
  timeout http-request 10s
  timeout queue   1m
  timeout connect 10s
  timeout client  1m
  timeout server  1m
  timeout http-keep-alive 10s
  timeout check   10s
  maxconn        3000

listen stats
  bind *:8080
```

```
mode http
stats enable
stats uri /haproxy
stats refresh 5s
stats realm haproxy-status
stats auth admin:password
```

```
listen jms-web
bind *:80
mode http
option httpchk GET /api/health/
stick-table type ip size 200k expire 30m
stick on src
balance leastconn
server 192.168.100.21 192.168.100.21:80 weight 1 cookie web01 check inter 2s rise 2 fall 3
server 192.168.100.22 192.168.100.22:80 weight 1 cookie web02 check inter 2s rise 2 fall 3
```

After modifying the configuration file, restart and enable HAProxy:

```
systemctl enable haproxy
systemctl start haproxy
```

JumpServer HA-cluster configuration

JumpServer (including Community Edition) fully supports HA clustering without any restrictions. In this article, I will show how it works.

Why is an HA cluster needed for JumpServer

An HA (High Availability) cluster for JumpServer is necessary to ensure high system availability and minimize downtime. It enables:

1. **Avoiding downtime:** If one cluster node fails, another continues to handle user requests.
2. **Ensuring fault tolerance:** Clustering allows the system to automatically switch to available nodes in case of errors.
3. **Improving performance:** Load is distributed across multiple nodes, enhancing system responsiveness under high user demand.
4. **Increasing data storage reliability:** Using shared resources like MySQL and Redis with clustering support minimizes the risk of data loss.
5. **Scalability:** The cluster can be easily expanded by adding more nodes to handle more users and tasks.

This architecture is particularly important for organizations where JumpServer is used as a critical access and control system.

Components of the JumpServer Cluster

Nodes/JumpServer Nodes - Core cluster nodes with JumpServer installed. Each server does not store "useful" data, making it possible to clone, copy, delete, or add nodes as needed.

Database MySQL/PostgreSQL - The main DBMS for storing all JumpServer data, including system settings, device parameters, user accounts, and passwords for target systems. By default, it also stores session text logs such as SSH commands, SQL queries, and keyboard input in RDP sessions.

By default, JumpServer creates and uses PostgreSQL within a container on the same server where JumpServer is installed.

Redis Database - An auxiliary database for caching. It can be a shared database for the entire cluster or separate databases for each cluster node.

By default, JumpServer creates and uses Redis within a container on the same server where JumpServer is installed.

Video Recordings Storage - By default, it stores session recordings in the folder **\$folder/core/data/media**, where **\$folder** is specified in the main configuration file (default: **VOLUME_DIR=/data/jumpserver**). The product's web interface allows setting up external video storage: **SFTP, S3, Ceph, Minio, and others**.

Command Logs Storage - Logs are stored in the main database by default. The web interface allows configuring log storage in **Elasticsearch**.

Load Balancer - Usually based on HAProxy, but other options can be used.

Cluster Architecture

Typically, a JumpServer cluster consists of two or more cluster nodes that:

- Are connected to a shared MySQL/PostgreSQL database (or cluster).
- Are connected to a shared Redis database (or each has its own).
- Share a common storage for video recordings:
 - A common folder **\$folder/core/data/** (usually implemented via an NFS server).OR
 - External storage for session recordings (e.g., SFTP, S3, Ceph, Minio).
- Share a common storage for command logs:
 - Based on a shared database (default).OR
 - Based on Elasticsearch.
- Use a load balancer (optional).

Example of creating a JumpServer HA Cluster with two nodes

Example of creating a JumpServer cluster

- With a shared MySQL database
- With a shared Redis database
- With a shared folder for storing video recordings **\$folder/core/data/** using an NFS server.

For this, we need:

1. **Server with NFS, MySQL, Redis:**
 - 4 CPUs, 8 GB of RAM.
2. **JumpServer Node1:**
 - 4 CPUs, 8 GB of RAM, 100 GB of free disk space.
3. **JumpServer Node2:**
 - 4 CPUs, 8 GB of RAM, 100 GB of free disk space.
4. **HAProxy Server** (or another load balancer).

1. Preparing the server with NFS, MySQL, and Redis

- **Server:** Ubuntu 22.04, IP: 10.10.50.10

Installing and configuring NFS

Commands may vary for different Linux versions, but generally, you need to create a shared folder:

```
sudo apt install nfs-kernel-server
sudo mkdir -p /data
```



```
sudo chown -R nobody:nogroup /data/  
sudo chmod 777 /data/  
sudo nano /etc/exports
```

Add the following line to the `/etc/exports` file:

```
/data 10.10.50.10/24(rw,sync,no_subtree_check)
```

Apply the settings and restart the NFS service:

```
sudo exportfs -a  
sudo systemctl restart nfs-kernel-server
```

Installing and configuring MySQL

Instructions depend on the OS version. To create a database and user, run the following commands:

```
mysql -uroot  
mysql> create database jumpserver default charset 'utf8';  
mysql> set global validate_password_policy=LOW;  
mysql> create user 'jumpserver'@'%' identified by 'KXOeyNgDeTdpeu9q';  
mysql> grant all on jumpserver.* to 'jumpserver'@'%';  
mysql> flush privileges;  
mysql> exit;
```

Don't forget to configure the firewall to open the MySQL port (`3306`).

Installing and configuring Redis

Instructions depend on the OS version. After installing Redis, run the following commands:

```
sed -i "s/bind 127.0.0.1/bind 0.0.0.0/g" /etc/redis.conf  
sed -i "561i maxmemory-policy allkeys-lru" /etc/redis.conf  
sed -i "481i requirepass KXOeyNgDeTdpeu9q" /etc/redis.conf
```

This will allow access to Redis with the password `KXOeyNgDeTdpeu9q`. Make sure to use a unique password for your server. Open the port `6379` in the firewall.

2. Installing JumpServer

Installing the first JumpServer node

Mounting the NFS Directory

Install the NFS client, mount the folder, and configure automatic mounting at startup:

```
sudo apt install nfs-common  
mkdir -p /opt/jumpserver/core/data
```

```
mount -t nfs 10.10.50.10:/data /opt/jumpserver/core/data
echo "10.10.50.10:/data /opt/jumpserver/core/data nfs defaults 0 0" >> /etc/fstab
```

Configuring JumpServer

Edit the `config-example.txt` file in the installer directory:

```
# Modify the following parameters, leave others as default.
# IMPORTANT: SECRET_KEY must match on all JumpServer nodes, or the data will not decrypt.

VOLUME_DIR=/opt/jumpserver

SECRET_KEY=
BOOTSTRAP_TOKEN=
LOG_LEVEL=ERROR
SESSION_EXPIRE_AT_BROWSER_CLOSE=True

# MySQL

DB_HOST=10.10.50.10
DB_PORT=3306
DB_USER=jumpserver
DB_PASSWORD=KXOeyNgDeTdpeu9q
DB_NAME=jumpserver

# Redis

REDIS_HOST=10.10.50.10
REDIS_PORT=6379
REDIS_PASSWORD=KXOeyNgDeTdpeu9q

# KoKo Lion
SHARE_ROOM_TYPE=redis
REUSE_CONNECTION=False
```

Run the installation:

```
./jmsctl.sh install
```

After the installation is complete, you will receive the following values:

```
SECRET_KEY=kWQdmdCQKjaWIHYpPhkNQDkfaRuIM6YnHctsHLISPs8287o2kW
BOOTSTRAP_TOKEN=KXOeyNgDeTdpeu9q
```

Installing the Second JumpServer Node

Install the NFS client and mount the folder just as on the first node.

When editing the JumpServer configuration file, **fill in the values for** `SECRET_KEY` **and** `BOOTSTRAP_TOKEN` obtained after installing the first node:

```
VOLUME_DIR=/opt/jumpserver
```

```
SECRET_KEY=kWQdmdCQKjaWIHYpPhkNQDkfaRuIM6YnHctsHLISPs8287o2kW
```

```
BOOTSTRAP_TOKEN=KXOeyNgDeTdpeu9q
```

```
LOG_LEVEL=ERROR
```

```
SESSION_EXPIRE_AT_BROWSER_CLOSE=True
```

```
# MySQL
```

```
DB_HOST=10.10.50.10
```

```
DB_PORT=3306
```

```
DB_USER=jumpserver
```

```
DB_PASSWORD=KXOeyNgDeTdpeu9q
```

```
DB_NAME=jumpserver
```

```
# Redis
```

```
REDIS_HOST=10.10.50.10
```

```
REDIS_PORT=6379
```

```
REDIS_PASSWORD=KXOeyNgDeTdpeu9q
```

```
# KoKo Lion
```

```
SHARE_ROOM_TYPE=redis
```

```
REUSE_CONNECTION=False
```

And run the installation:

```
./jmsctl.sh install
```

Result

After completing the setup, you will have two JumpServer nodes sharing one MySQL/Redis server and NFS storage. You can use any of the nodes to access target devices or configure HAProxy to automatically redirect users to an active node.

Getting Started Guide

Getting Started Guide for JumpServer PoC

Adding Devices

1. Preparation

Prepare two devices (for SSH and RDP) and one database to test the product features.

For example:


IP/Host Name	Port	Type	Account
afidc.afi.local	3389	Windows	testadmin
10.10.53.210	22	Linux	sergg
10.10.53.3	3306	MySQL	user

If you need to gather information about the **Windows** device, change local account passwords, create new accounts, or perform other tasks, you must configure **SSH for Windows**.

For RDP connections, this is **not required**.

2. Editing the Asset Tree

Go to the **Console - Assets - Assets** section and open the **Asset Tree** tab. Right-click in this section to open the asset tree editing menu.



You can create folders (**Nodes**) and subfolders for your devices (use the **Create node** option). Devices can be sorted into these folders.

- A device can belong to multiple folders simultaneously.
- These folders can be used to manage access policies, for example, granting access to all devices in a specific folder.

3. Adding Assets to the System

Add a Linux-based device. Windows, MySQL, and other devices are added similarly.

Click the **Create** button, select the device type **Linux** (under **Host**), and fill in the fields:

- **Name:** Any meaningful name
- **IP/Host:** The IP address or DNS name of the device
- **Platform:** Linux
- **Node:** Folder(s) where the device will be placed

Adjust port numbers if non-standard ports are used.

The screenshot shows the 'AFI Lab' console interface. The left sidebar contains a navigation menu with 'Console' selected. The main content area is titled 'Basic' and contains the following fields:

- Name:** Lab_Rabbit
- IP/Host:** 10.10.53.210
- Platform:** Linux
- Node:** /AFI-LabLinux

Below the 'Basic' section is the 'Protocol' section, which includes a table of protocols:

Protocol	Port	Settings	Remove	Add
ssh	22			
sftp	22			

Below the 'Protocol' section is the 'Account' section, which includes a table of accounts:

Account list	Name	Username	Privileged	Template add	Actions
No Data					

Below the 'Account' section is the 'Other' section, which includes a 'Domain' dropdown menu and a 'Label' dropdown menu.

4. Configuring Device Access Permissions

Go to **Console - Policies - Authorization** and click the **Create** button. Fill in the required access parameters:

The screenshot shows the 'AFI Demo' console interface. The left sidebar contains a navigation menu with 'Console' selected. The main content area is titled 'Update the asset authorization rules' and contains the following sections:

- Basic:** Name: full access
- User:** Users: TST_User(TST_User), Administrator(admin), test-nlo(test-nlo), testnlo.s(testnlo.s); Groups: AD Group_test
- Asset:** Assets: Select; Nodes: /AFI Demo
- Account:** Accounts: ☒ All existing accounts, ☐ Specified accounts, ☒ Virtual accounts; Virtual accounts: ☒ Manual account, ☒ Same account, ☐ Anonymous account
- Protocol:** Protocols: ☒ All protocol, ☐ Specific protocol

Name: A meaningful name for the access group

Users: The PAM user(s) who will gain access to the devices

Groups: User group(s) that will gain access

Assets: The device(s) to which access is granted

Nodes: Folder(s) containing the devices to which access is granted

Account:

- **All accounts:** Allow connections with any existing account for each device
- **Specified accounts:** Specify particular accounts for connection

- **Virtual accounts:** enable additional auth options
- **Manual account:** Allow manual login credentials without adding the account to the system
- **Same account:** Use the same account as the user's PAM login (LDAP authorization only)
- **Anonymous account:** Connect without credentials, typically for web interfaces where users input their login credentials manually

Protocol: Limit the protocol used for connections

Actions: Enable or disable file transfers, clipboard sharing, or session sharing permissions if supported by the connection type.

Actions

Actions

☒ All

☒ Connect ⓘ

☒ Transfer

☒ Upload ⓘ
 ☒ Download ⓘ
 ☒ Delete ⓘ

☒ Clipboard

☒ Copy ⓘ
 ☒ Paste ⓘ

☒ Share ⓘ

The effects of each permission vary, click the icon next to the permission to view.

You can enable or disable the policy and set its start and end time:

Other

Active ☒

Date start

Date expired

Comment

Click **Submit** to save the settings.

5. Connecting to Devices

Go to the Web Terminal by clicking the button in the top-right corner:



In the terminal, users see only the devices they are permitted to access. Click on the desired device in the list to select the account and connection type:

Connect - MySQL afisql.afi.local

✕

MYSQL

Select account

user

Connect Method

Web

Native

Applet

☒ Web CLI

☐ Web GUI

Advanced option

Remember selected

☐ Automatic Login next time (right click asset Connection to re-select)

Connect

Without additional configuration, you can connect via the web interface using **SSH**, **RDP**, and **SFTP**, as well as to **MySQL** via **Web CLI** or **Web GUI**. Other connection types, such as Kubernetes, web interfaces, RemoteApp applications, and databases using dedicated clients, will be covered in other articles.

Main configuration

Main configuration

Active Directory synchronization with AD groups

Configuring Integration with Active Directory

1. Go to "**System settings**" - "**Auth**" and select the **LDAP** tab.
2. Enter the LDAP server address, an account for connection, and its password.
3. Specify the OU and user search filter. See an example of a filter for a specific group in the screenshot below.

The screenshot shows the 'Auth' configuration page in the system settings. The 'LDAP' tab is selected. The 'Basic' section has a toggle for 'Enable LDAP auth' which is turned on. Below it, the 'LDAP server' field contains 'ldap://afldc.afs.local:389' with a hint 'eg: ldap://localhost:389'. The 'Bind DN' field contains 'testadmin@afs.local' and there is a 'Password' field. The 'LDAP User' section has a 'User OU' field with 'DC=afs,DC=local' and a hint 'Use | split multi OUs'. The 'User search filter' field contains '(&(objectClass=user)(memberOf=CN=AFI_IT,CN=Users,DC=afs,DC=local))' with a hint 'Choice may be (cn|uid|sAMAccountName)=%(user)s'. The 'User attr map' field contains a JSON object:

```
1 {
2   "username": "sAMAccountName",
3   "name": "cn",
4   "email": "mail"
5 }
```

4. Click the "**Submit**" button to save the settings. Note: After changing parameters and settings, always click "**Submit**" to apply changes. Otherwise, the test will run with old parameters.
5. Click the "**Test connection**" button to verify the settings or "**Test login**" to check a specific user's authorization.

6. Click the **"Bulk Import"** button. You should see the users of the group that will be added for PAM authorization. You can select specific users and click **"Import"** or import all users by clicking **"Import all"**.

7. You can also configure automatic user synchronization by clicking the **"Sync setting"** button.

The screenshot shows a 'Sync setting' dialog box with the following fields and controls:

- * Organization:** A dropdown menu showing 'Default' with a close button (x).
- Periodic perform:** A toggle switch that is currently turned on.
- Regularly perform:** A text input field containing the cron expression `*/15 * * * *`. Below this field, there is explanatory text: 'For example: every Sunday at 03:05 execute <5 3 * * 0>', 'Using the 5-bit Linux crontab expression <minute hour day month week> ([Online tool](#))', and 'If both regularly perform and cycle perform execution are set, use regularly perform first'.
- * Cycle perform:** A text input field containing the value '1'. Below this field, it says 'Unit: hour'.
- Recipient:** A dropdown menu showing 'Select'.
- Buttons:** 'Reset' and 'Submit' buttons at the bottom.

Synchronization with Active Directory Groups

Why synchronize with AD groups?

Managing access rights to target systems can be done using familiar Active Directory groups. Adding or removing a user from such groups will automatically synchronize with the permissions matrix in JumpServer, and the user will gain or lose access rights.

Configuring synchronization with AD groups.

1. Go to **System settings - Authentication - LDAP**
2. In the **User attribute** field, add the parameter **groups** to look like this:

```
{
  "username": "sAMAccountName",
  "name": "cn",
  "email": "mail",
  "groups": "memberOf"
}
```

See screenshot:

Basic

LDAP



* Server ?

ldap://afidc.afi.local:389

* Bind DN ?

testadmin@afi.local

Password ?

Password

Search

* Search OU ?

DC=afi,DC=local

* Search filter ?

(&(objectClass=user)(memberOf=CN=AFI_IT,CN=Users,DC=afi,DC=local))

* User attribute ?

1

2

3

4

5

6

"username": "sAMAccountName",

"name": "cn",

"email": "mail",

"groups": "memberOf"

}

3. Click the **Submit** button to save the settings.

4. Click the **User Import** button and then click **Sync Users** in the opened window.

If everything is correct, you will see a list of users and a column with AD group attributes:

Ldap user

Please submit ldap configuration before import

Search

<input type="checkbox"/>	Username	Name	Email	Groups	Already exists
<input type="checkbox"/>	denis	Морозов Денис	-	CN=TestJS,OU=subOU,OU=TestOU,DC=afi,DC=local CN=AFI_IT...	Yes
<input type="checkbox"/>	sergey	Попцов Сергей	-	CN=AFI_IT,CN=Users,DC=afi,DC=local	Yes
<input type="checkbox"/>	nlo	Наталия Орлова	no@afi-d.ru	CN=TestJS,OU=subOU,OU=TestOU,DC=afi,DC=local CN=thyc...	Yes
<input type="checkbox"/>	Вася	Вася	-	CN=TestJS,OU=subOU,OU=TestOU,DC=afi,DC=local CN=AFI_IT...	Yes
<input type="checkbox"/>	testnlo	testnlo	-	CN=AFI_IT,CN=Users,DC=afi,DC=local CN=Domain Admins,CN...	Yes
<input type="checkbox"/>	TST_User	TST_User	-	CN=AFI_IT,CN=Users,DC=afi,DC=local	Yes

Total 6

15/page

< 1 >

Sync users

Import

Import all

Cancel

5. Click **Import all** to add users to the system.

If you go to **Console - User - Groups**, you will see JS user groups with AD group names and the same users in them:

JumpServer

Console

Dashboard

USER

User

Groups

ASSETS

Assets

Zones

Platforms

ACCOUNTS

Groups

+ Create


Actions

<input type="checkbox"/>	Name	Users
<input type="checkbox"/>	AD AFL_IT	6
<input type="checkbox"/>	AD Domain Admins	2
<input type="checkbox"/>	AD Remote Desktop Users	1
<input type="checkbox"/>	AD TestJS	3
<input type="checkbox"/>	AD thycotic	1
<input type="checkbox"/>	Default	16

Command filter configuration for SSH and database queries

Command ACL Configuration

1. Go to the "**Console - Policies - ACLs - Command filter**" section and open the "**Command Group**" tab.
2. Click the "**Create**" button, enter a name for the list, such as "**Common high-risk commands**", and fill in the list with the required commands or regular expressions (see the screenshot). Save it by clicking the "**Submit**" button.



The screenshot shows the 'Command group update' interface. On the left is a sidebar with navigation links: Console, Dashboard, Users, Assets, Accounts, Permissions (expanded), Asset permissions, User login acl, Command acl (selected), Asset connect acl, Connect method acl, and More... The main area is titled 'Command group update' and contains a 'Basic' tab. The form fields are: Name (Common high-risk commands), Type (Command selected, Regex unselected), Content (rm, rmdir, chattr, su), Ignore case (toggle on), and Comment (empty). At the bottom are 'Reset' and 'Submit' buttons.

3. Open the "**Command filter**" tab and click "**Create**" to create a filter.
4. The filter configuration includes the following parameters:
 - **Priority:** the filter priority. The action of the filter with the highest priority will always be executed.
 - **User:** JumpServer users for whom the filter will apply.
 - **Asset:** target systems where the filter will control connections.
 - **Account:** accounts on target systems that will be controlled by the filter.
 - **Command Group:** groups of commands that will be blocked.
 - **Action:** the filter action: **Reject** - block the command, **Accept** - execute the command, **Review** - send the command for approval by a specified employee, **Warning** - warn the specified employee about executing the command.

AFI-Platform

AFI-Lab

99+

Console

Dashboard

Users

Assets

Accounts

Permissions

Asset permissions

User login acl

Command acl

Asset connect acl

Connect method acl

More...

Basic

Name

Common high-risk commands

Priority

50

1-100, the lower the value will be match first

User

User

AllUsers

SpecificUsers

Select By Attribute

Полное Срепей(sergey)

Наталия Орлова(nlo)

Asset

Asset

AllAsset

SpecificAsset

Select By Attribute

JumpServer22(10.10.53.22)

Account

Account

All accounts

Specify account

Command group

Command group

Common high-risk commands

Action

Action

Reject

Accept

Review

Warning

5. Click "**Submit**" to save the settings.

Main configuration

How to enable 2FA(TOTP) auth

In the **Community Edition**, two-factor authentication via **TOTP** (Google Authenticator) is available.

To enable it, go to **System setting - Security - Auth Security**. The **Global MFA auth** parameter allows you to disable two-factor authentication or enable it for all users or only for administrators.

Note: For **TOTP** to work correctly, the JumpServer server must configure the NTP service to obtain the correct time.

MFA

Global MFA auth

☐ Not enabled ☒ All users ☐ Only admin users

MFA in login page

☐

Eu security regulations(GDPR) require MFA to be on the login page

Third-party login users perform MFA authentication

☐

The third-party login modes include OIDC, CAS, and SAML2

* MFA verify TTL

Unit: second, The verification MFA takes effect only when you view the account password

OTP issuer name

* OTP valid window

Reset

Submit

In **JumpServer Enterprise**, other two-factor authentication options are also available, such as two-factor authentication via **RADIUS**.

Main configuration

Installing OpenSSH for account management for Windows

Why Install OpenSSH on Windows Devices?

OpenSSH on Windows is used for gathering system information, rotating passwords for local Windows accounts, and automatically creating local accounts.

If you only need to connect via RDP without managing accounts, **OpenSSH is not required**.

Installing OpenSSH

Simply run the installation distribution OpenSSH-Win64.msi with administrative rights. No configuration is needed.

For more secure connections, you can configure authentication using a **private key**.

Configuring Authentication with a Private Key

- [Setting Up Public Key-Based Authentication for Windows](#)

```
ssh-keygen.exe -t rsa
cp %env:USERPROFILE%.ssh\id_rsa.pub %env:USERPROFILE%.ssh\authorized_keys
```

```
notepad C:\ProgramData\ssh\sshd_config
```

```
# This is the sshd server system-wide configuration file. See
# sshd_config(5) for more information.

# The strategy used for options in the default sshd_config shipped with
# OpenSSH is to specify options with their default value where
# possible, but leave them commented. Uncommented options override the
# default value.

#Port 22
#AddressFamily any
#ListenAddress 0.0.0.0
#ListenAddress ::
```

```
#HostKey __PROGRAMDATA__/ssh/ssh_host_rsa_key
#HostKey __PROGRAMDATA__/ssh/ssh_host_dsa_key
#HostKey __PROGRAMDATA__/ssh/ssh_host_ecdsa_key
#HostKey __PROGRAMDATA__/ssh/ssh_host_ed25519_key

# Ciphers and keying
#RekeyLimit default none

# Logging
#SyslogFacility AUTH
#LogLevel INFO

# Authentication:

#LoginGraceTime 2m
#PermitRootLogin prohibit-password
StrictModes no
#MaxAuthTries 6
#MaxSessions 10

PubkeyAuthentication yes

# The default is to check both .ssh/authorized_keys and .ssh/authorized_keys2
# but this is overridden so installations will only check .ssh/authorized_keys
AuthorizedKeysFile .ssh/authorized_keys

#AuthorizedPrincipalsFile none

# For this to work you will also need host keys in %programData%/ssh/ssh_known_hosts
#HostbasedAuthentication no
# Change to yes if you don't trust ~/.ssh/known_hosts for
# HostbasedAuthentication
#IgnoreUserKnownHosts no
# Don't read the user's ~/.rhosts and ~/.shosts files
#IgnoreRhosts yes

# To disable tunneled clear text passwords, change to no here!
#PasswordAuthentication yes
#PermitEmptyPasswords no

# GSSAPI options
#GSSAPIAuthentication no

#AllowAgentForwarding yes
#AllowTcpForwarding yes
#GatewayPorts no
#PermitTTY yes
#PrintMotd yes
#PrintLastLog yes
```

```
#TCPKeepAlive yes
#UseLogin no
#PermitUserEnvironment no
#ClientAliveInterval 0
#ClientAliveCountMax 3
#UseDNS no
#PidFile /var/run/sshd.pid
#MaxStartups 10:30:100
#PermitTunnel no
#ChrootDirectory none
#VersionAddendum none

# no default banner path
#Banner none

# override default of no subsystems
Subsystem sftp sftp-server.exe

# Example of overriding settings on a per-user basis
#Match User anoncvs
# AllowTcpForwarding no
# PermitTTY no
# ForceCommand cvs server

# Uncomment the following two lines:
#Match Group administrators
# AuthorizedKeysFile __PROGRAMDATA__/ssh/administrators_authorized_keys
```

```
net stop sshd
net start sshd
```

Using a Private Key

```
ssh user@ip -i <private_key_absolute_path> (local users)
ssh user@domain@ip -i <private_key_absolute_path> (Domain users)
```

Syslog configuration

1. Modifying the JumpServer Configuration File

The configuration files for JumpServer are located at: `/opt/jumpserver/config/config.txt`

The following elements need to be added to the JumpServer configuration:

```
# Syslog Configuration
SYSLOG_ENABLE=true
SYSLOG_ADDR=10.1.12.116:514 # Syslog server IP and port
SYSLOG_FACILITY=local2 # Corresponds to the Syslog configuration file
```

2. Restarting JumpServer

After modifying the JumpServer configuration file, you need to restart the service to apply the changes.

Command:

```
jmsctl restart
```

3. Verifying the Configuration

Log into the JumpServer service to generate a login event log and check for output on the Syslog server. Example login event log:

```
[root@jumpserver ~]# cat /tmp/messages
Apr 18 16:27:23 10.1.14.125 root: message:rsyslog logging From JumpServer
Apr 18 16:27:42 10.1.14.125 root: message:rsyslog logging From JumpServer(UDP)
Apr 18 16:40:42 10.1.14.125 jumpserver: login_log - {"backend": "Password", "backend_display": "密码", "city": "局域网", "datetime": "2023/04/18 16:34:08 +0800", "id": "adf0e434-e306-4693-9a51-23f256cb025d", "ip": "10.1.10.35", "mfa": {"label": "禁用", "value": 0}, "reason": "", "reason_display": "", "status": {"label": "成功", "value": true}, "type": {"label": "Web", "value": "W"}, "user_agent": "Mozilla/5.0 (Windows NT 10.0; Win64; x64; rv:109.0) Gecko/20100101 Firefox/111.0", "username": "admin"}
```

4. Analyzing Syslog Information

Event Type	Syslog Record Example
Login	Apr 19 15:25:11 10.1.14.125 jumpserver: login_log - {"backend": "Password", "backend_display": "password", "city": "local", "datetime": "2023/04/19 15:18:36 +0800", "id": "cfc378e5-6337-4bf9-a8ac-15f33c2b0314", "ip": "10.1.10.35", "mfa": {"label": "disabled", "value": 0}, "reason": "", "reason_display": "", "status": {"label": "successful", "value": true}, "type": {"label": "Web", "value": "W"}, "user_agent": "Mozilla/5.0 (Windows NT 10.0; Win64; x64) AppleWebKit/537.36 (KHTML, Gecko) Chrome/112.0.0.0 Safari/537.36 Edg/112.0.1722.48", "username": "admin"}

File Upload	Apr 19 15:27:26 10.1.14.125 jumpserver: ftp_log - {"account": "root(root)", "asset": "10.1.12.182-root(10.1.12.182)", "date_start": "2023/04/19 15:20:51+0800", "filename": "/tmp/vmware-root/file.pdf" , "id": "6e7721c0-2091-49fb-8853-fc18e0a2e432", "is_success": true, "operate": {"label": "uploading", "value": "upload" }, "org_id": "00000000-0000-0000-0000-000000000002", "remote_addr": "10.1.10.35", "user": "Administrator(admin)"}
File Download	Apr 19 15:28:08 10.1.14.125 jumpserver: ftp_log - {"account": "root(root)", "asset": "10.1.12.182-root(10.1.12.182)", "date_start": "2023/04/19 15:21:33+0800", "filename": "/tmp/vmware-root/file.pdf" , "id": "113c0601-80c1-47d1-a053-5038fd89698c", "is_success": true, "operate": {"label": "downloading", "value": "download" }, "org_id": "00000000-0000-0000-0000-000000000002", "remote_addr": "10.1.10.35", "user": "Administrator(admin)"}

RemoteApp configuration for application publishing

Note: The Community Edition supports only the HTTP application publishing mode.

RemoteApp is the publication of applications on Microsoft RDS. To use it, you need a Windows Server with configured RDS (RemoteApp). **JumpServer** can connect to applications published on the RDS server and authorize in them. This is mainly relevant for database management and web interface applications.

To support RemoteApp, you need to configure JumpServer and the RDS server.

Requirements:

- MS Windows Server 2016 or MS Windows Server 2019
- Installed RDS (Remote Desktop Services) role

Configured WinRM or installed OpenSSH

Adding a Publishing Server to JumpServer

Go to **"System settings - Applets"**, select the **"Remote Hosts"** tab, and click **"Create"**.

The screenshot shows the 'Applets' configuration page in JumpServer. The left sidebar contains a menu with 'Applets' selected. The main content area is divided into three sections: 'Basic', 'Protocol', and 'Account'.

Basic

- Name:** afirds afl local
- IP/Host:** afirds afl local

Protocol

Protocols table:

Protocol	Port	Enabled	Actions
rdp	3389	<input checked="" type="checkbox"/>	⊗ ⊕
ssh	22	<input checked="" type="checkbox"/>	⊗ ⊕
winrm	5985	<input checked="" type="checkbox"/>	⊗ ⊕ +

Asset support protocol is limited by platform, click the Settings button to view the protocol settings. If you need to update, please update the platform

Account

Account list table:

Name	Username	Privileged	Template add	Actions
testadmin	testadmin	<input checked="" type="checkbox"/>	-	⊗ ⊕

Using same account: ☐ Connect to the host using the same account first. For security reasons, please set the configuration item CACHE_LOGIN_PASSWORD_ENABLED=true and restart the service to enable it.

Auto create accounts: ☒ These accounts are used to connect to the published application, the account is now divided into two types, one is dedicated to each account, each user has a private account, the other is public, when the application does not support multiple open and the special has been used, the public account will be used to connect

Accounts create amount: 100 The number of public accounts created automatically


Parameter Descriptions:

Parameter	Description
name	Device name
IP/Host	IP address or network name of the RDS server
protocol group	Protocols and port numbers. Specify WinRM or SSH if OpenSSH will be used
Account List	An administrator account for accessing the RDS server
Automatically create an account	Enable automatic account creation for connecting to published applications
Number of accounts created	Number of accounts to be created
Core service address	The communication address between the agent of the remote application publishing machine and JumpServer backend. Replace http:127.0.0.1 with your server's IP address
RDS license	Configure the RDS license server
RDS License Server	RDS license server parameters
RDS authorization mode	Choose "Device" or "User" to configure the authorization mode.
RDS single user single session	Choose "Disable" or "Enable" to configure the single session mode for one user.
RDS maximum disconnect time	When the session reaches this maximum time, the connection is terminated.
RDS remote application logout time limit	Time to log out after the remote application session is disconnected.


Click **"Submit"** to save the settings.

Setting Up the Application Publishing Mechanism

Click on the name of the added publishing server. Server information will open; go to the **"Remote host deployment"** tab and click the **"Deploy"** button on the right side of the screen.




An installation window will appear, showing the installation process:



Application Publishing

You do not need to manually install applications on the RDS server; JumpServer provides ready-made applets that will automatically install and publish the required applications. Existing applets are available on the online portal, where you can download them.

To publish an application, go to the **"Remote Apps"** tab. Here you can see the list of added applets, their status, and the **"Deploy"** and **"Uninstall"** buttons for installing and removing applets from the publishing server.




If the applet status is **"Success"**, you can add devices and connect to them using the corresponding applications. For connecting to web interfaces (**HTTP**), you can use the **Chrome** or **Firefox** applets.

How to configure access to asset web-interface, HTTP session configuration

To connect to target systems via HTTP, you need to [configure browser publishing via Panda](#) (Linux-based application publishing server) or **RDS (RemoteApp)**. [RDS \(RemoteApp\) configuration instructions](#).

Creating a "Website" Type Device

1. Go to the **"Console - Assets"** section, click the **"Create"** button, and select the target system type - **Website**.



The screenshot shows the JumpServer console interface. On the left is a sidebar with a menu: Console, Dashboard, Users, Assets (selected), Domains, Platforms, Accounts, Permissions, and More... The main area is titled 'Basic' and contains the following fields:

- Name:** Script Simple Form Authentication
- URL:** https://authenticationtest.com/simpleFormAuth/
- Platform:** Website
- Node:** JF-LAB


Below these is the **Selector** section with three radio buttons: **Autofill** (Disabled), **Basic** (selected), and **Script**. Under 'Basic', there are three input fields:

- Username selector:** name=email
- Password selector:** name=password
- Submit selector:** XPath=/html/body/div/div/div[2]/form/input

Below the selector section is the **Protocol** section with a dropdown for **Protocols** set to 'http(s)' and a port field set to '443'. A small note below says: 'Asset support protocol is limited by platform, click the Settings button to view the protocol settings. If you need to update, please update the platform.'

At the bottom is the **Account** section with an 'Account list' and a link 'Update account information in asset details'.

2. In the **"Selector"** section, specify the parameters of the form fields that **JumpServer** will fill automatically when starting a session.
For example:




This block shows a detailed view of the 'Selector' configuration. It includes the same radio buttons as the previous image: **Autofill** (Disabled), **Basic** (selected), and **Script**. Below them are three input fields:

- Username selector:** name=email
- Password selector:** name=password
- Submit selector:** XPath=/html/body/div/div/div[2]/form/input

With these settings, the username will be entered into the HTML element with **name="email"**, the password will be entered into the HTML element with **name="password"**, and then the button with **Xpath=/html/body/div/div/div[2]/form/input** will be clicked.


You can inspect the web form elements in the browser by right-clicking on the input field and selecting "Inspect" (in Firefox) or "View Page Source" (in Chrome). Additionally, you can use advanced settings and parameters of the login form elements by switching to **Script** mode:



3. In the **Account list** section, add the username and password to be used for authorization, similar to other connection types.
4. Save the settings by clicking the **"Submit"** button.

Connecting to Web Interfaces via Web Terminal

If everything is configured correctly, when selecting the desired device in the web terminal, you will see a session start option:



Setting up Panda for application publishing(alternative to RemoteApp)

JumpServer supports using both Windows Server and Linux as application publishing machines, such as for publishing Chrome and Firefox browsers for HTTP sessions and various database clients.

Types of Application Publishing:

Microsoft RemoteApp: A method of publishing applications based on Windows Server, providing maximum smoothness. Requires additional configuration of Windows Server and the purchase of Microsoft RDS CALs.

Panda (Virtual Application): A Linux-based application publishing method, characterized by medium smoothness, good compatibility, and support for operating systems like CentOS, RedHat, Kylin, and openEuler.

Setting Up Panda for Application Publishing

Principle of Operation:

The Linux-based application publishing machine uses container technology to isolate the application in an independent runtime environment. The Panda component provided by JumpServer manages virtual applications.

The process looks as follows:


1. The user accesses the JumpServer Web Terminal and connects to the selected virtual application.
2. The Panda component creates a GUI container based on VNC and forwards the VNC connection information to the Lion component.
3. The Lion component connects to the container.

Deployment Schemes

Scheme 1: All in One

Using the server where JumpServer is deployed as a machine for publishing virtual applications.

192.168.127.162



1. Configuring the Main Configuration File

Open the main JumpServer configuration file.

```
nano /opt/jumpserver/config/config.txt
```

Add the following parameters to it:


```
# Enable the Panda component
PANDA_ENABLED=1
# Enable virtual applications in the core
VIRTUAL_APP_ENABLED=1
# Panda host IP address (JumpServer IP)
PANDA_HOST_IP=192.168.127.162
# URL for Lion to connect to Panda
PANDA_HOST=http://panda:9001
```

Restart the JumpServer service to apply the changes.

```
[root@localhost ~]# jmsctl restart
```

2. Enabling the Virtual Applications Feature

In the JumpServer management console, go to **System Settings** → **Features** → **VirtualApp** and activate the virtual applications feature.




3. Loading Virtual Applications

Download virtual applications locally. Currently supported applications include: **Chrome, DBeaver**. Distributions for these applications are available on the [vendor portal](#). Applications for Panda are located in the Virtual App section, while others are only for RemoteApp (RDS).

In the JumpServer management console, navigate to **System Settings** → **RemoteApps** and upload the virtual applications in the **VirtualApp** section.

After a short wait, the application will automatically be deployed on the application publishing machine. In the JumpServer management console, under **System Settings** → **RemoteApps** → **Application Providers** → **VirtualApp**, you can see the successful deployment of the application.




4. Using Virtual Applications

Connect to assets using virtual applications.

Note: At this point, the JumpServer service will launch the virtual application container: **2970298425/docker-chrome-app:v0.1.0** (Note: this container is approximately 1.3GB in size and requires downloading over the Internet. In a local network, it can be manually downloaded).

Scheme 2: Panda on a Separate Server



1. Configuring the Main Configuration File

Open the main JumpServer configuration file.

```
nano /opt/jumpserver/config/config.txt
```

Add the following parameters to it:

```
# Enable the Panda component
PANDA_ENABLED=0
# Panda IP for the Lion component
PANDA_HOST=http://192.168.127.163:9001
```

Restart the JumpServer service to apply the changes.

```
[root@localhost ~]# jmsctl restart
```

2. Installing Panda on a Separate Machine

Unpack the JumpServer installation package on the publishing machine, install Docker and Docker Compose, and load the image.

```
[root@panda ~]# tar xzvf jumpserver-offline-release-v3.10.6-amd64.tar.gz -C /opt
```

Install Docker and Docker Compose:

```
[root@panda ~]# cd /opt/jumpserver-offline-release-v3.10.6-amd64/scripts
[root@panda scripts]# ./2_install_docker.sh
```

Load the Panda image:

```
[root@panda scripts]# cd images
[root@panda images]# docker load -i panda:v3.10.6.tar
```

Create a docker-compose file for Panda:

```
[root@panda ~]# mkdir -p /data/jumpserver/panda/data
[root@panda ~]# mkdir -p panda
[root@panda ~]# cd panda
[root@panda panda]# cat docker-compose.yaml
version: '2.4'

services:
  panda:
    image: registry.fit2cloud.com/jumpserver/panda:v3.10.6
    container_name: jms_panda
    hostname: jms_panda
    ulimits:
      core: 0
    restart: always
    ports:
      - 9001:9001
    tty: true
    environment:
      - BOOTSTRAP_TOKEN=YmEyNTRkNTYtNDIyMi02OTJm
      - CORE_HOST=http://192.168.127.162
      - NAME=panda
```



```
- PANDA_HOST_IP=192.168.127.163
volumes:
- /data/jumpserver/panda/data:/opt/panda/data
- /var/run/docker.sock:/var/run/docker.sock:z
healthcheck:
test: "curl -fsL http://localhost:9001/panda/health/ > /dev/null"
interval: 10s
timeout: 5s
retries: 3
start_period: 10s
```

BOOTSTRAP_TOKEN is taken from the JumpServer configuration file: /opt/jumpserver/config/config.txt

CORE_HOST - The address of your JumpServer

PANDA_HOST_IP - The IP address of Panda

Start the Panda container:

```
docker-compose up -d
```

3. Enabling the Virtual Applications Feature

Repeat the steps from the All in One section.

4. Loading Virtual Applications

Repeat the steps from the All in One section.


5. Using Virtual Applications

Repeat the steps from the All in One section.

Troubleshooting

How to check system status and container logs

JumpServer is installed as a set of Docker containers performing various functions.



To check the state of the containers, log in to the server where JumpServer is installed and enter the following command:

```
# docker ps -a
```

All containers in the list should have the status **Healthy**

List of Containers

```
jms_panda  
jms_magnus  
jms_celery  
jms_chen  
jms_koko  
jms_lion  
jms_razor  
jms_video  
jms_web  
jms_redis  
jms_kael  
jms_xrdp  
jms_mysql  
jms_core
```

To view the error log of a specific module, use the following command:

```
docker logs -f #CONTAINER_NAME --tail 200
```

For example:

Web interface error log:

```
docker logs -f jms_web --tail 200
```

Error log for Panda:

```
docker logs -f jms_panda --tail 200
```

RemoteApp Troubleshooting

Description of the Interaction Between JumpServer, RDS Server, and Tinker

In this article, I will describe in detail how JumpServer, RDS Server, and Tinker interact so that any issues can be identified.

Description of the RDS and JumpServer Integration Process

1. JumpServer connects to the RDS server via SSH:

- Installs the Tinker service on the RDS server and specifies the JS address (Core API parameter).
- Creates local service accounts of the type `js_*` and `jms_*` on the RDS server.
- Adds the created accounts to the "Remote Desktop Users" group.

“ Important: The "Remote Desktop Users" group name may differ in Windows, depending on the OS language. If these accounts are not present in the group, you will need to add them manually.

1. Tinker connects to JumpServer at the specified address (Core API parameter):

- Tinker reports that it is running, and the RDS status changes to "online".
- Downloads distributions of selected applets, such as Chrome and DBeaver, from the JS server using the same address specified in the Core API. Other applets may be downloaded from the internet. If there is no internet access, you can manually install the required applications.
- Tinker installs the downloaded applets

Description of Tinker

Tinker is an auxiliary application for integration with JumpServer, assisting in maintaining communication between RDS and JS, installing applications (applets) required for publication, and managing the publication of RemoteApp applications during session initiation.

- By default, it is installed in the folder:
`C:\Users\[ACCOUNT]\AppData\Local\Programs\Tinker\`
(`[ACCOUNT]` is the account used for the integration of JS and RDS.)

- It installs the **JumpServer Tinker Service** - this service must always be running.
- Detailed logs of Tinker's operation and errors are available in the folder:

`C:\Users\[ACCOUNT]\AppData\Local\Programs\Tinker\data\logs`

Tinker Applets

Applets are a set of applications and automation scripts for managing applications. By default, applets are installed in the folder:


`C:\Program Files\JumpServer`

This folder contains executable applications and Python scripts with launch parameters that you can modify if necessary.

Final Checklist

- **OpenSSH** is installed on Windows RDS, and port **22** is open on the Windows firewall.
- The account used for integration with RDS has **administrator rights** on the RDS server.
- The **IP/Host** field contains the **IP address** of the RDS server or its **DNS name**, which can be resolved by JumpServer.
- The **Core API** field contains the **URL of JumpServer**, accessible from the RDS Server.
- Accounts of the type `JS_XX` and `JMS_XX` are created on the RDS server.
- Accounts of the type `JS_XX` and `JMS_XX` are members of the **Remote Desktop Users** group on the RDS server.
- The **JumpServer Tinker Service** is running on the RDS server.
- The **RDS server status** in the JumpServer interface: **Normal**.
- The **Status of applets** in the properties of the RDS server in the JumpServer interface: **Success**.

Here are some screenshots for example:



Basic

* Name

* IP/Host

Protocol

Protocols

ssh	22		
rdp	3389		

The protocols supported by the assets are restricted by the platform. Click the settings button to view the protocol settings. If updates are required, please update the platform

Account

Accounts [Update account info in asset details](#)

Using same account ☐

Auto create accounts ☒

Accounts create amount

Automation

Core API

Ignore certificate verification ☒

Existing RDS license ☐

System settings

General

Organizations

Roles

Platforms

Notifications

Features

Authentication

Storage

Components

RemoteApp

Security

Appearance

Tools

System tasks

License

← RemoteApp

RemoteApp

RemoteApp machine

VirtualApp

Application providers

When connecting to an asset, the selection of the application publishing machine is random (but the last used one is preferred). If you want to specify when selecting an account for the publishing machine, the following situations will choose the user's own account with the same name or password:

1. both the publishing machine and application support concurrent;

2. the publishing machine supports concurrent, but the application does not, and the current application does not use a proprietary account;

3. the publishing machine does not support concurrent, the application either supports or does not support concurrent, and no application uses a proprietary account.

note: whether the application supports concurrent connections is decided by the developer, and whether the host supports concurrent connections is decided by the platform.

Create

Actions

<input type="checkbox"/>	Name	IP/Host	Protocols
<input type="checkbox"/>	afirds.afi.local	afirds.afi.local	ssh:22 rdp:3389

Total 1

RemoteApp machine: afirds.afi.local

Basic Accounts RemoteApp Deploy publishing machine Activities

RECENT (7 DAYS)

Recently discovered | Recently logged in | Recently modified | Recently changed password | Recent password change failed

RISKY ACCOUNT

No login for long time | Add account | Weak password | Empty password | Long time password

ACCOUNT TYPE

All Host | Database | Cloud | Device | Web | Other

+ Create Account templates Actions					Search			
<input type="checkbox"/>	Name	Username	Asset	Connect	Actions			
<input type="checkbox"/>	jms_5VODdjer	jms_5VODdjer	afirds.afi.local					
<input type="checkbox"/>	jms_62IQmV1	jms_62IQmV1	afirds.afi.local					
<input type="checkbox"/>	jms_D66i2Sp5	jms_D66i2Sp5	afirds.afi.local					
<input type="checkbox"/>	jms_EKj8v3N	jms_EKj8v3N	afirds.afi.local					
<input type="checkbox"/>	jms_Ear7CsCq	jms_Ear7CsCq	afirds.afi.local					
<input type="checkbox"/>	jms_JRXD9cYj	jms_JRXD9cYj	afirds.afi.local					
<input type="checkbox"/>	jms_O58h7ro4	jms_O58h7ro4	afirds.afi.local					
<input type="checkbox"/>	jms_YWj71Nn2	jms_YWj71Nn2	afirds.afi.local					
<input type="checkbox"/>	jms_ppOf6H3m	jms_ppOf6H3m	afirds.afi.local					
<input type="checkbox"/>	jms_wQ000Ri	jms_wQ000Ri	afirds.afi.local					
<input type="checkbox"/>	js_ACUNETIX	js_ACUNETIX	afirds.afi.local					
<input type="checkbox"/>	js_ACUNETIX8	js_ACUNETIX8	afirds.afi.local					
<input type="checkbox"/>	js_AFIDC	js_AFIDC	afirds.afi.local					
<input type="checkbox"/>	js_AFIDC8	js_AFIDC8	afirds.afi.local					

Basic Accounts RemoteApp Deploy publishing machine Activities

Search



<input type="checkbox"/>	Name	Version	Date	Release status	Actions	
<input type="checkbox"/>	Base	0.2.2	04/02/2025 11:24:19	Success	Deploy...	Uninst...
<input type="checkbox"/>	Mong	0.2.2	04/02/2025 11:24:36	Success	Deploy...	Uninst...
<input type="checkbox"/>	Firefc	0.2.0	04/02/2025 11:25:04	Success	Deploy...	Uninst...
<input type="checkbox"/>	DBea	0.3	04/02/2025 11:25:40	Success	Deploy...	Uninst...
<input type="checkbox"/>	Chro	1.1	04/02/2025 11:25:40	Success	Deploy...	Uninst...

Total 5

15/page

< 1 >

Quick update

Initialization deployment

Deployment

Only initial deployment

Deployment

Publish all applications

Publish

Additional features

Custome Applet structure for RemoteApp

What is an applet?

An applet is a set of files that describe the process of installing and launching an application on Microsoft RDS via RemoteApp. This is necessary for JumpServer to initiate an access session to this application, automatically log in, and hide the authorization parameters from the user.

Applet Structure

Each applet must include the following files:

```
AppletName
├── i18n.yml
├── icon.png
├── main.py
├── manifest.yml
└── setup.yml
```

main.py - script for launching and logging into the application

icon.png - applet icon

manifest.yml - metadata, i.e., applet description

setup.yml - file describing the installation process

i18n.yml - file for translation into various languages

File manifest.yml

Example based on the MySQL Workbench applet

The file manifest.yml contains general information about the applet and specifies its type and protocol.

```
# (required)
name: mysql_workbench8
display_name: "{{ 'MySQL Workbench' | trans }}"
comment: "{{ 'A tool for working with MySQL, to execute SQL and design tables' | trans }}"
# (required)
version: 0.1.1
# (required)
```

```

exec_type: python
# (required)
author: Eric
# general or web (required)
type: general
update_policy: always
edition: community
# (required)
tags:
  - database
# (required)
protocols:
  - mysqlworkbench

# translations into other languages
i18n:
  MySQL Workbench:
    en: MySQL Workbench
    zh: MySQL Workbench
    ja: MySQL Workbench

A tool for working with MySQL, to execute SQL and design tables:
  en: A tool for working with MySQL, to execute SQL and design tables
  zh: MySQL SQL
  ja: MySQL SQL

```

File setup.yml

The file setup.yml describes the parameters for installing the applet on the RDS server.

```

# software installation type - msi, exe, zip, manual
type: msi
# URL to download the software distribution or file name if the distribution is included with the applet
# archive
source: mysql-workbench-community-8.0.31-winx64.msi
# installation arguments
arguments:
  - /qn
  - /norestart
# installation directory
destination: C:\Program Files\MySQL\MySQL Workbench 8.0 CE
# path and name of the executable file
program: C:\Program Files\MySQL\MySQL Workbench 8.0 CE\MySQLWorkbench.exe
md5: d628190252133c06dad399657666974a

```

Script main.py

main.py - the main script of the applet

The application is launched by running the command:

```
python main.py base64_json_data
```

That is, the main.py script is launched, and the launch parameters are passed to it. The **base64_json_data** structure looks approximately as follows:

```
{
  "app_name": "mysql_workbench8",
  "protocol": "mysql",
  "user": {
    "id": "2647CA35-5CAD-4DDF-8A88-6BD88F39BB30",
    "name": "Administrator",
    "username": "admin"
  },
  "asset": {
    "asset_id": "46EE5F50-F1C1-468C-97EE-560E3436754C",
    "asset_name": "test_mysql",
    "address": "192.168.1.1",
    "protocols": [
      {
        "id": 2,
        "name": "mysql",
        "port": 3306
      }
    ]
  },
  "account": {
    "account_id": "9D5585DE-5132-458C-AABE-89A83C112A83",
    "username": "root",
    "secret": "test"
  },
  "platform": {
    "charset": "UTF-8"
  }
}
```

Contents of main.py

```
import sys

from common import (block_input, unblock_input) # Import functions for blocking/unblocking input
from common import convert_base64_to_dict # Import function to convert Base64 string to a dictionary (array)
from app import AppletApplication # Import main application

def main():
    base64_str = sys.argv[1] # Get the Base64 string from command-line arguments
    data = convert_base64_to_dict(base64_str) # Convert Base64 string to a dictionary
    # The data dictionary contains all the parameters for launching the application: account, server
```

```

name, database name, etc., depending on the application type
    applet_app = AppletApplication(**data) # Pass dictionary data to the application launch function
    block_input() # Block user input
    applet_app.run() # Launch the application
    unblock_input() # Unblock user input
    applet_app.wait() # Wait for the application to complete

if __name__ == '__main__':
    try:
        main() # Launch the main function
    except Exception as e:
        print(e) # Output the error if it occurs

```

Contents of app.py

App.py typically contains all the main code for launching the application with the required parameters, making it the most important and complex part when developing a new applet. It is easier to base it on one of the scripts of existing applets that are similar in structure/type to the new applet being developed.

```

import sys # Imports the sys module for working with system functions

if sys.platform == 'win32': # Checks if the operating system is Windows
    from pywinauto import Application # Imports the library for automating Windows GUI applications
    from pywinauto.controls.uia_controls import (
        ButtonWrapper, EditWrapper, MenuItemWrapper,
        MenuWrapper, ComboBoxWrapper, ToolbarWrapper
    )
    # Imports various controls for interacting with the application's GUI

from common import BaseApplication, wait_pid # Imports the base application class and a function
for waiting on processes

_default_path = r"C:\Program Files\MySQL\MySQL Workbench 8.0 CE\MySQLWorkbench.exe"
# Defines the default path to the MySQL Workbench application

class AppletApplication(BaseApplication): # Defines the application class inheriting from
BaseApplication

    def __init__(self, *args, **kwargs): # Initializes the application
        super().__init__(*args, **kwargs) # Calls the parent class constructor

        self.path = _default_path # Sets the application's path
        self.username = self.account.username # Retrieves the username from the account information
        self.password = self.account.secret # Retrieves the password from the account information
        self.host = self.asset.address # Retrieves the host address from the asset information
        self.port = self.asset.get_protocol_port(self.protocol) # Retrieves the port based on the protocol
        self.db = self.asset.spec_info.db_name # Retrieves the database name

```

```

self.pid = None # Placeholder for the application's process ID
self.app = None # Placeholder for the application object

def run(self): # Method to run the application
    app = Application(backend='uia') # Creates an application object using UI Automation
    app.start(self.path) # Starts the application using the specified path
    self.pid = app.process # Saves the application's process ID
    if not all([self.username, self.password, self.host]): # Checks if necessary parameters are
provided
        print('7F51125F89764C2769') # Outputs an error message in Chinese ("Missing required parameters")
        return

    # Accesses the main MySQL Workbench window and the "Database" menu
    menubar = app.window(title="MySQL Workbench", auto_id="MainForm",
control_type="Window") \
        .child_window(title="Database", control_type="MenuItem")
    menubar.wait('ready', timeout=10, retry_interval=5) # Waits for the menu to be ready
    MenuItemWrapper(menubar.element_info).select() # Opens the "Database" menu

    # Selects the "Connect to Database" menu item
    cdb = menubar.child_window(title="Connect to Database", control_type="MenuItem")
    cdb.wait('ready', timeout=10, retry_interval=5) # Waits for the item to be ready
    MenuItemWrapper(cdb.element_info).click_input() # Clicks on "Connect to Database"

    # Inputs the host
    host_ele = app.top_window().child_window(title="Host Name", auto_id="Host Name",
control_type="Edit")
    EditWrapper(host_ele.element_info).set_edit_text(self.host) # Sets the host value

    # Inputs the port
    port_ele = app.top_window().child_window(title="Port", auto_id="Port", control_type="Edit")
    EditWrapper(port_ele.element_info).set_edit_text(self.port) # Sets the port value

    # Inputs the username
    user_ele = app.top_window().child_window(title="User Name", auto_id="User Name",
control_type="Edit")
    EditWrapper(user_ele.element_info).set_edit_text(self.username) # Sets the username value

    # Inputs the database name
    db_ele = app.top_window().child_window(title="Default Schema", auto_id="Default Schema",
control_type="Edit")
    EditWrapper(db_ele.element_info).set_edit_text(self.db) # Sets the database name

    # Clicks the "OK" button to confirm the connection
    ok_ele = app.top_window().child_window(title="Connection", auto_id="Connection",
control_type="Window") \
        .child_window(title="OK", control_type="Button")
    ButtonWrapper(ok_ele.element_info).click() # Clicks "OK"

    # Inputs the password

```

```
password_ele = app.top_window().child_window(title="Password", auto_id="Password",
control_type="Edit")
password_ele.wait('ready', timeout=10, retry_interval=5) # Waits for the password field to be
ready
EditWrapper(password_ele.element_info).set_edit_text(self.password) # Sets the password value

# Clicks "OK" to complete the connection
ok_ele = app.top_window().child_window(title="Button Bar", auto_id="Button Bar",
control_type="Pane") \
    .child_window(title="OK", control_type="Button")
ButtonWrapper(ok_ele.element_info).click() # Clicks "OK"

self.app = app # Saves the application object for further use

def wait(self): # Method to wait for the application to complete
    wait_pid(self.pid) # Waits for the process with the specified ID to complete
```